

NRT solo Setup

Download: http://www.nashrealtime.com/NRT_Install.exe

Preliminary system settings:

1. **Turn OFF Aero mode** (Aero creates multiple handles to windows, making it impossible for NRT to track the game tables)
2. **Turn ON User account control.** You need it ON to set exe's in properties to run as admin. After exe's have been set, you can turn it off again, if desired.
3. **Set display to high 32 Bit** (It most likely is at this setting by default.)

Install and Setup:

1. Download and save NRT installer
2. Run NRT installer
3. Set Vista User Security - User account privileges on Program Folder - All Exe to Admin ([skip for XP systems](#))
4. Start NRT and set Hand History Locations and Options
5. Set Folder security for Hand History folders (optional)
6. Check Poker Site settings
7. PH pro owners: copy pokerhound.license from PH program folder (C:\Program Files (x86)\Insight\PokerHound) to NRT install folder (C:\Program Files (x86)\Insight\NRT)
8. First time PH product trial users - NRT will run free for 7 days
9. Previous PH product trial users, request special Trial license. Currently, download : http://www.nashrealtime.com/NRT_Sept_2009.license and place in NRT install folder (C:\Program Files (x86)\Insight\NRT). **Free usage until Sept. 1, 2009**
10. Hold'em Manager users, uncheck "Track Live Hands" That feature is not compatible with NRT solo. (It uses code, which I sold them, that injects into Poker Site. Only one application can inject into poker site at a time.)
11. Play a SNG to test setup

Note: This process only needs to be done on initial install. Your system will remember the settings for subsequent installs and updates.

Poker Stars

1. Install English version preferably to default location
2. Set Hand History Save location
3. Set Deck to Standard

Cereus (UB & AP)

1. Install English version preferably to default location
2. Set Hand History Save location
3. Set Dealer Messages to Everything
4. Set Table to Top View and Default size (future update will support other table sizes)

iPoker

1. Install English version preferably to default location
2. Set chat and table options

Party Poker

1. Install English version to default location
2. Install FPHG, set folder security, **and set to XP emulation**
Download Link: http://www.insight-pokerhound.com/FreePHG_Install.exe

Full Tilt

Currently, Full Tilt is supported Post-Game only.
Load your Hand History files into NRT Replay

Typical NRT Option settings:

Note: If you are cascading tables, do NOT check "Always Show NRT"

If you only play a couple of tables at same time, uncheck "Disable Next SB Line"

NRT Settings

Save Cancel

General:

- Start Real-Time as Icon
- Hide EV Lines Post-Pockets:
- Disable Next SB Line:
- Disable XML save of scanned game:

Auto-Start Calculation:

- Game Level at x BB: 100
- Stack <= x BB: 20

Always Show NRT:

- Cereus FT Party iPoker Stars

Cereus:

- NRT EV Dif Wam min EV (Red) / Mid EV (Yellow): 0.3 / 0.6
- NRT Stack Wam min (Red) / Mid (Yellow): 0.7 / 1.4

iPoker:

- NRT EV Dif Wam min EV (Red) / Mid EV (Yellow): 0.3 / 0.6
- NRT Stack Wam min (Red) / Mid (Yellow): 0.7 / 1.4

Party Poker:

- NRT EV Dif Wam min EV (Red) / Mid EV (Yellow): 0.3 / 0.6
- NRT Stack Wam min (Red) / Mid (Yellow): 0.7 / 1.4

Full Tilt:

- NRT EV Dif Wam min EV (Red) / Mid EV (Yellow): 0.2 / 0.5
- NRT Stack Wam min (Red) / Mid (Yellow): 0.7 / 1.4

Poker Stars:

- NRT EV Dif Wam min EV (Red) / Mid EV (Yellow): 0.2 / 0.5
- NRT Stack Wam min (Red) / Mid (Yellow): 0.7 / 1.4